

**JKB00218**

19/09/2002

## Configuring CockpIT for an NT4 Domain

### General:

The CockpIT default setting is for an Active Directory environment. A few changes must be made manually to connect CockpIT to NT4 Domains.

### Method:

#### 1. Edit the CockpIT Registry.

CockpIT Server Registry settings are located under the following path:

**HKEY\_LOCAL\_MACHINE\SOFTWARE\Jetro\JDS**

Change the following parameters:

Parameter	Default setting (Active Directory)	Setting for NT4
ADSearchMode	0	1
AuthenticationPath	LDAP://domain name (dns)	WinNT://domain name (netbios)

#### 2. Edit the Global.asa file

Global.asa is a settings file located in the installation sub-folder 'site'. The default CockpIT Server installation folder is:

'C:\Program Files\CockpITServer'

Open the Global.asa in the notepad and make sure that the following line is configured to the correct NT4 domain.

**Application("DOMAIN")="Domain name"** (netbios name)

#### 3. Check the services logon account name.

CockpIT includes three services that require a special username in order to operate: JDS, JTSmonitor and JDSNetExplorer. Make sure that this user account has administrator level permission in the Domain and the local server.